

THE CAMERA

Crochet Bag & Purse

crochet
pattern



Materials:

- (1) 100% acrylic DK / Light Worsted.
- (2) Crochet hook **3.75 - 4.5 mm. (US F-5, G-6, 7)**
- (3) Felt (Black and White).
- (4) Black plastic zipper ~ 9 inch. (or Magnetic snaps (sew on).
- (5) Wood button ~15 - 20 mm.
- (6) Embroidery thread (black and white).
- (7) Yarn needle and embroidery needle.
- (8) Scissors.

Size:

~w 21 cm. (8 inch) x h 21 cm. (8 inch).

Gauge/inch: 5-6

Skill Level: Intermediate

100% Acrylic DK


A:
80g

B:
60g

20g

Abbreviations:

	English	Thai
MR	Magic Ring	วงกันหอย
slst	Slip Stitch	เลื่อนห่วง (ลห)
st	Stitch	หลัก
ch	Chain	โซ่
sc	Single Crochet	ควักธรรมดา (คธ)
blsc	Black Loop Single Crochet	ควักธรรมดาบนห่วงหลัง
inc	Increase	คธ.เพิ่มห่วง

View fingers (felt)

01: 3.7x3.7 cm.


02: 2.4x2.4 cm.

03: 1.5x1.5 cm.

04: 3.7x1.5 cm.

Bag x 1

Rnd.	Pattern	Sts.
	Color A , Start from base, Base chain – sl knot, chain 35.	35
1	sc 2 into 2nd chain from hook , sc each ch on next 32 sts, sc 3 on next ch (the first ch of the base chain). Turn sideways and continue along another side of the base chain, sc each ch on next 33 sts, slst to the ch st at the beginning round.	70
2	ch 1, [*sc on next st, sc 2 on next st, sc each on next 32 sts, sc 2 on next st,] * 2 times, slst, then sl st(slip stitch) around , slst to the sc st at the beginning round.	74
3-21	ch1, sc around ,slst, then slst around , slst to the sc st at the beginning round.	74
22	Color B, blsc around , slst.	74
23-24	ch1, sc around , slst.	74
	Fasten off, weave the yarn end.	



Camera Lens #1 x 1		
Rnd.	Pattern	Sts.
1	Black , 9 sc in Magic Ring, slst.	9
2	ch 1, (inc) *9 times, slst.	18
3	ch 1, (sc 1, inc) *9 times, slst.	27
4	ch 1, (sc 2, inc) *9 times, slst.	36
5	ch 1, Black (sc 3, inc) *2 times, White (sc 3, inc) *2 times, Black (sc 3, inc) *5 times, slst.	45
6	ch 1, (sc 4, inc) *9 times, slst.	54
7	White , ch 1, sc around, slst.	54
Fasten off, weave the yarn end. Leave the back yarn ~30cm.		

Camera Lens #2 x 1		
Rnd.	Pattern	Sts.
	White , Start from chains 54, slst to close circle	54
1	ch 1, sc around, slst.	54
Fasten off, leave the yarn ~30 cm. Sew to the lens #1.		

Strap x 1		
Row.	Pattern	Sts.
	Color B , sl knot, chain 4. (leave the yarn ~25-30 cm.)	
1	sc into 2nd chain from hook , sc each ch on next 2 sts, turn.	3
2-200	Ch1, sc across, turn.	3
	Fasten off, leave the yarn ~25-30 cm. You can adjust the wide strap from sc 3 - sc 5. The length also you can adjust the row form your body.	



Cover x 1		
Rnd.	Pattern	Sts.
	Color B , Start from base, Base chain – sl knot, chain 35.	35
1	sc 2 into 2nd chain from hook , sc each ch on next 32 sts, sc 3 on next ch (the first ch of the base chain). Turn sideways and continue along another side of the base chain, sc each ch on next 33 sts, slst to the ch st at the beginning round.	70
2	ch 1, [*sc on next st, sc 2 on next st, sc each on next 32 sts, sc 2 on next st,] * 2 times, slst, then sl st (slip stitch) around , slst to the sc st at the beginning round.	74
3-8	ch1, sc around ,slst, then slst around , slst to the sc st at the beginning round.	74
	Fasten off, leave the yarn ~50 cm. Sew to the bag.	

ASSEMBLY



1. **Color A**, start from the base, Rnd.2, then slst around.




2. Crochet follow the pattern.



3. Finished rnd.21.



4. **Color B**, Crochet follow the pattern (rnd.22-24).



5. Sew the viewfinder felts onto the cover (middle).



6. The cover.



7. Sew the zippers.



8. Mark the lens into the right position.



9. Sew the lens.

ASSEMBLY



10. Sew the cover.



11. Sew the strap left and right side.



12. Last, sew the wood button into the left lens position.