

CROCHET PATTERN

PLUSH BACKPACK BUNNY



***Crochet Pattern contains 7 pages, 38 photos ***

I want to thank you so much for the purchase.

This pattern doesn't contain crochet lessons.

For working on this pattern, basic crochet skills are required.

Skills level - intermediate.

Any child will be happy with such a plush backpack bunny. Crochet it as a gift to someone or for your child.

Recommended materials and tools

- ✓ Super Bulky/Super Chunky/14ply velvet yarn HIMALAYA DOLPHIN BABY - 2 skeins of different colors
- ✓ Sport weight/4ply yarn YarnArt JEANS or Alize Cotton Gold of black color 30 cm thread for face decoration
- ✓ Sewing needle
- ✓ Hook size 3.75 mm and 5 mm by Clover
- ✓ Wooden button
- ✓ Safety eyes 8-10 mm
- ✓ Safety nose 10 mm
- ✓ Stuffing toy material

Note:

- Work in continuous rounds, in rows and in a spiral.
- The size of the backpack - 21 cm wide (8.2 "), 24 cm high (9.4 ").
- At the beginning of the round, use a marker or thread of a different color so that you can see where the beginning of the round is.

Abbreviations:

ch - chain

MR - magic ring

sc - single crochet

inc - increase

dec - decrease

sl st - slip stitch

BLO - back loops only

t-ch - turning chain

hdc - half double crochet stitch

hdcinc - half double crochet increase (2 hdc in one stitch)

hdc2tog - crochet 2 hdc together

(...) * n - repeat instruction in brackets N times

(...) - number of loops in a row / round

FLAP

Crochet with pink yarn. Work in rows.

1) ch2, crochet 5 sc into the 2nd ch from the hook. Do not pull the ring. Turn. (5)

2) t-ch, 1 sc, inc * 4, turn (9)

3) t-ch, (sc, inc) * 4, 1 sc, turn (13)

4) t-ch, (2 sc, inc) * 4, 1 sc, turn (17)

5) t-ch, (3 sc, inc) * 4, 1 sc, turn (21)

6) t-ch, (4 sc, inc) * 4, 1 sc, turn (25)

7) t-ch, (5 sc, inc) * 4, 1 sc, turn (29)

8) t-ch, (7 sc, inc) * 3, 5 sc, turn (32)

9) t-ch, (8 sc, inc) * 3, 5 sc (35)

Do not turn. Work along the top of the flap.

10) t-ch, 19 sc, turn (19)

11-15) t-ch, 19 sc, turn (5 rows)


16) t-ch, 19 sc (19)

Do not turn.

Change color to purple. Cut the pink yarn. Then work in rounds.

17) t-ch, 22 sc, 3 ch, skip 3 stitches, 22 sc, turn (47)

18) t-ch, 47 reverse sc (47), sl st



BACKPACK

Begin to crochet with purple yarn.

Ch20. Start on the second chain from the hook:

1) 18 sc, 3 sc in the last chain, on the other side of the chain: 17 sc, inc, inc into t-ch (42)

Place a marker.

2) 16 sc, (inc, 1 sc) * 2, inc, 15 sc, (inc, 1 sc) * 3 (48)

3) inc, 15 sc, (inc, 1 sc) * 4, inc, 14 sc, (inc, 1 sc) * 4, 1 sc (58)

4) inc, 15 sc, (inc, 3 sc) * 3, inc, 17 sc, (inc, 3 sc) * 3 (66)

5) inc, 18 sc, (inc, 4 sc) * 3, inc, 16 sc (inc, 4 sc) * 3 (74)

6) 74 sc (74)

7) BLO 74 sc (74)

8-16) 74 sc (9 rounds)

17) 26 sc, dec, 34 sc, dec, 10 sc (72)

Change color to pink. Cut the purple yarn.

18-35) 72 sc (18 rounds)

Join the flap in the next rounds

36) 71 sc, 1 sc with the flap (72)

37) 20 sc with the flap, 52 sc (72), sl st.



STRAPS

Crochet with purple yarn. Work in rows.

1) ch71, start from the second chain on the hook: 70 sc, turn (70)

2-4) t-ch, 70 sc (3 rows)

You can make the straps longer or shorter. Make more or less chains.

My straps are 50 cm long.

Cut the yarn. Leave the end for sewing pieces. If chenille yarn crumbles a lot, it is better to sew on the straps with a cotton thread matches the color.

Sew the straps at the bottom of the backpack between rounds 7 and 11, at the top of the backpack between rounds 32 and 36. Distance between straps 12 sc.



HANDLE

Crochet with purple yarn. Work in rows.

1) ch21, start from the second chain on the hook: 20 sc, turn (20)

2-3) t-ch, 20 sc (20 rows)

Cut the yarn. Leave the end for sewing pieces. If chenille yarn crumbles a lot, it is better to sew on the handle with a cotton thread matches the color.

Sew on the handle.



CORD

Ch150. Step back at the top of the backpack 2 rounds and stretch the cord between the stitches, after folding the backpack, as shown in the photo.

Make knots at the ends.





Sew a button between rounds 23 and 27.



BUNNY

HEAD

Crochet with milk yarn.

- 1) ch2, crochet 6 sc into the 2nd ch from the hook (6)
- 2) inc *6 (12)
- 3) (1 sc, inc) * 6 (18)
- 4) 1 sc, inc (2 sc, inc) * 5, 1 sc (24)
- 5) (3 sc, inc) * 6 (30)
- 6) (4 sc, inc) * 6 (36)
- 7-10) 36 sc (4 rounds)
- 11) (4 sc, dec) * 6 (30)
- 12) (3 sc, dec) * 3 (24)

Cut the yarn. Leave the end for sewing pieces. If chenille yarn crumbles a lot, it is better to sew on the head with a cotton thread matches the color.

Insert safety eyes between rounds 4 and 5. Distance between eyes 6-7 sc. Insert the safety nose into the middle of the amigurumi ring. Before you secure it with a washer, embroider the mouth with a pink thread.

Stuff the head. Sew the head to the flap of the backpack. Sew through walls of stitches from above, not through, so that there are no stitches on the wrong side of the cover





EARS (make 2)

Crochet with milk yarn. Crochet with hook 5 mm

- 1) ch2, crochet 6 sc into the 2nd ch from the hook (6)
- 2) hdcinc * 6 (12)
- 3) (hdc, hdcinc) * 6 (18)
- 4) (5 hdc, hdcinc) * 3 (21)
- 5-6) 21 hdc (2 rounds)
- 7) (5 hdc, hdc2tog) * 3 (18)
- 8) 18 hdc (18)
- 9) (4 hdc, hdc2tog) * 3 (15)
- 10-11) 15 hdc (2 rounds)
- 12) (3 hdc, hdc2tog) * 3 (12)
- 13-14) 12 hdc (2 rounds)
- 15) (2 hdc, hdc2tog) * 3 (9)
- 16-17) 9 hdc (2 rounds)
- 18) 9 sc (9)



Fold it in half and crochet 4 sc through both sides.

Leave the end for sewing pieces. If chenille yarn crumbles a lot, it is better to sew on the head with a cotton thread ears the color.

Sew on the ears.

Embroider lashes with a black cotton thread.



CONGRATULATIONS!!!
YOUR PLUSH BACKPACK BUNNY IS READY