

CROCHET PATTERN

PLUSH BACKPACK UNICORN



***Crochet Pattern contains 9 pages, 51 photos ***

Dear friends!

I want to thank you so much for the purchase.

This pattern doesn't contain crochet lessons.

For working on this pattern, basic crochet skills are required.

Skills level - intermediate.

Any child will be happy with such a plush backpack unicorn. Crochet it as a gift to someone or for your child.

Recommended materials and tools

- ✓ Super Bulky/Super Chunky/14ply velvet yarn HIMALAYA DOLPHIN BABY - 2 skeins of the pink color, 1/4 of dark pink color, a little of cream color for the head and different colors for the mane and tail.
- ✓ Sport weight/4ply yarn YarnArt JEANS or Alize Cotton Gold of yellow color for the horn
- ✓ Sewing needle
- ✓ Hook size 3.75, 2.25 & 3 mm by Clover
- ✓ Wooden button
- ✓ Safety eyes 15 mm
- ✓ Stuffing toy material

Note:

- Work in continuous rounds, in rows and in a spiral.
- The size of the backpack - 21 cm wide (8.2 "), 24 cm high (9.4 ").
- At the beginning of the round, use a marker or thread of a different color so that you can see where the beginning of the round is.

Abbreviations:

ch - chain

MR - magic ring

sc - single crochet

inc - increase

dec - decrease

sl st - slip stitch

BLO - back loops only

t-ch - turning chain

(...) * n - repeat instruction in brackets N times

(...) - number of loops in a row / round

Tip: If plush yarn is crumble, use cotton thread matching color to sew on pieces.

FLAP

Crochet with pink yarn. Work in rows.

1) ch2, crochet 5 sc into the 2nd ch from the hook. Do not pull the ring. Turn. (5)

2) t-ch, 1 sc, inc * 4, turn (9)

3) t-ch, (sc, inc) * 4, 1 sc, turn (13)

4) t-ch, (2 sc, inc) * 4, 1 sc, turn (17)

5) t-ch, (3 sc, inc) * 4, 1 sc, turn (21)

6) t-ch, (4 sc, inc) * 4, 1 sc, turn (25)

7) t-ch, (5 sc, inc) * 4, 1 sc, turn (29)

8) t-ch, (7 sc, inc) * 3, 5 sc, turn (32)

9) t-ch, (8 sc, inc) * 3, 5 sc (35)

10) t-ch, (9 sc, inc) * 3, 5 sc (38)

Do not turn. Work along the top of the flap.

11) t-ch, 21 sc, turn (21)


12-18) t-ch, 21 sc, turn (6 rows)

19) t-ch, 21 sc (21). Do not turn.

Change color to dark pink. Cut the pink yarn. Then work in rounds. Crochet the yarn ends after color changing into stitches of the next row.

20) t-ch, 25 sc, ch3, skip 3 stitches, 25 sc, turn (53)

21) t-ch, 53 reverse sc (53), sl st



BACKPACK

Crochet with pink yarn

Ch20. Start on the second chain from the hook:

1) 18 sc, 3 sc in the last chain, on the other side of the chain: 17 sc, inc, inc into t-ch (42)

Place a marker.

2) inc, 15 sc, (inc, 1 sc) * 2, inc, 17 sc, (inc, 1 sc) * 2 (48)

3) inc, 1 sc, inc, 15 sc, (inc, 1 sc) * 4, inc, 15 sc, (inc, 1 sc) * 3 (58)

4) inc, 1 sc, inc, 16 sc, (inc, 3 sc) * 3, inc, 18 sc, (inc, 3 sc) * 2 (66)

5) inc, 3 sc, inc, 18 sc, (inc, 4 sc) * 3, inc, 17 sc (inc, 4 sc) * 2 (74)

6) 74 sc (74)

7) BLO 74 sc (74)

8-16) 74 sc (9 rounds)

17) 32 sc, dec, 35 sc, dec, 3 sc (72)

18-36) 72 sc (19 rounds)

Join the flap in the next round

37) 1 sc, 23 sc with the flap, 48 sc (72), sl st.



STRAPS

Crochet with dark pink yarn. Work in rows.

1) ch71, start from the second chain on the hook: 70 sc, turn (70)

2-4) t-ch, 70 sc (3 rows)

You can make the straps longer or shorter. Make more or less chains. My straps are 50 cm long.

Cut the yarn. Leave the end for sewing pieces.

Sew the straps at the bottom of the backpack between rounds 7 and 11, at the top of the backpack between rounds 32 and 36. Distance between straps 12 sc.



HANDLE

Crochet with pink yarn. Work in rows.

1) ch21, start from the second chain on the hook: 20 sc, turn (20)

2-3) t-ch, 20 sc (20 rows)

Cut the yarn. Leave the end for sewing pieces.

Sew on the handle.



CORD

Crochet with pink yarn.

Ch150. Step back at the top of the backpack 2 rounds and stretch the cord between the stitches, after folding the backpack, as shown in the photo.

Make knots at the ends.

Sew a button between rounds 23 and 27.



UNICORN

HEAD

Begin to crochet with cream yarn.

1) ch2, crochet 6 sc into the 2nd ch from the hook (6)

2) inc *6 (12)

3) (1 sc, inc) * 6 (18)

4) 1 sc, inc (2 sc, inc) * 5, 1 sc (24)

5-7) 24 sc (3 rounds)

Change color to pink. Cut the cream yarn.

8) 24 sc (24)

9) 9 sc, 6 inc, 9 sc (30)

10) 9 sc, (1 sc, inc) * 6, 9 sc (36)

11) (5 sc, inc) * 6 (42)

12-14) 42 sc (3 rounds)

Insert safety eyes between rounds 10 and 11.

Distance between eyes 10-11 sc.

15) (5 sc, dec) * 6 (36)

16) 2 sc, dec, (4 sc, dec) * 5, 2 sc (30)

17) (3 sc, dec) * 6 (24)

Stuff the head.

Leave the end for sewing pieces.



EARS (make 2)

Crochet with pink yarn. Crochet with hook 3 mm.

1) ch2, crochet 4 sc into the 2nd ch from the hook (4)

2) (1 sc, inc) * 2 (6)

3) (2 sc, inc) * 2 (8)

4) (1 sc, inc) * 4 (12)

5) 12 sc (12)

6) (3 sc, dec) * 2 (10)

Cut the yarn. Leave the yarn tail to sew pieces.



HORN

Crochet with cotton yellow yarn. Crochet with hook 2.25 mm

- 1) 6 sc in MR (6)
- 2) (2 sc, inc) * 2 (8)
- 3) 8 sc (8)
- 4) (3 sc, inc) * 2 (10)
- 5) 10 sc (10)
- 6) (4 sc, inc) * 2 (12)
- 7) 12 sc (12)
- 8) (3 sc, inc) * 3 (15)
- 9) 15 sc (15)
- 10) (4 sc, inc) * 3 (18)
- 11) 18 sc (18) sl st.



Cut the yarn. Leave the yarn tail for sewing. Stuff the horn.

Strands for the mane and tail (make 10)

You can crochet them in a different color or in the same color.

Ch 40, from the second chain on the hook: 39 inc. Fasten off and cut the yarn. Leave the end for sewing.



FORELEGS (make 2)

Crochet with dark pink yarn.

- 1) ch2, crochet 6 sc into the 2nd ch from the hook (6)
- 2) inc * 6 (12)
- 3) (3 sc, inc) * 3 (15)
- 4) BLO 15 sc (15)

Change color to pink. Cut the dark pink yarn.

- 5-6) 15 sc (2 rounds)
- 7) dec, 13 sc (14)
- 8) dec, 12 sc (13)



9) dec, 11 sc (12)

10) dec, 10 sc (11)

11) dec, 9 sc (10)

12-13) 10 sc (2 rounds)

Stuff the lower foreleg. Fold it in half and crochet 5 sc through both sides. Cut the yarn. Leave the yarn tail for sewing pieces.

HIND LEGS (make 2)

Begin to crochet with dark pink yarn.

1) ch2, crochet 6 sc into the 2nd ch from the hook (6)

2) inc * 6 (12)

3) (1 sc, inc) * 6 (18)

4) BLO 18 sc (18)

Change color to pink. Cut the dark pink yarn.

5-6) 18 sc (2 rounds)

7) (7 sc, dec) * 2 (16)

8) (6 sc, dec) * 2 (14)

9) dec, 12 sc (13)

10) dec, 11 sc (12)

11) dec, 10 sc (11)

12) dec, 9 sc (10)

13) 10 sc (10)

Stuff the lower leg. Fold it in half and crochet 5 sc through both sides. Cut the yarn. Leave the yarn tail to sew pieces.



ASSEMBLY

1. Sew the ears between rounds 13 and 16 of the head at a distance of 7 sc.
2. Sew the horn to the head between rounds 11 and 13.
3. Embroider nostrils and lashes with dark pink chenille thread.
4. Sew the head to the flap of the backpack.
5. Sew on the hind legs between rounds 8 and 11.
6. Sew forelegs between rounds 22 and 27.
7. Sew 5 strands to the head.
8. Sew 5 strands of the tail to the back between the straps.



**CONGRATULATIONS!!!
YOUR PLUSH BACKPACK UNICORN IS READY**

